Install BlackBox on MT5


A flight recorder for every fill on your account. Free · read-only, never opens or closes trades · about 5 minutes.

Step 1 — Get your key and the EA

Sign in at www.indicatorfree.com (Sign in, top right).


Open your BlackBox page: My account → Open BlackBox, or go straight to www.indicatorfree.com/account/blackbox. The top menu BlackBox → Open my dashboard leads there too.

In Connect your MT5 account (Add another MT5 account once you have one), press the gold Download IndicatorFree-BlackBox-….ex5 button, then press Copy next to Your BlackBox key. One key works for all your MT5 accounts and terminals — keep it to yourself.




Step 2 — Open the MT5 data folder

In MT5, choose File → Open Data Folder (Ctrl+Shift+D).




Step 3 — Copy the EA into MQL5\Experts

In the window that opens, go into MQL5, then Experts.




Name	Date modified	Type	Size
bases	8/26/2026 6:29 AM	File folder	
config	10/24/2026 6:16 AM	File folder	
liveupdate	10/23/2026 11:15 AM	File folder	
llm-agent	8/26/2026 6:39 AM	File folder	
logs	10/24/2026 3:13 AM	File folder	
MQL5	2/13/2026 2:00 PM	File folder	
temp	11/19/2025 8:37 PM	File folder	
Tester	11/12/2025 11:52 AM	File folder	
origin.txt	11/5/2025 7:51 PM	Text Document	1 KB

Paste the downloaded IndicatorFree-BlackBox-….ex5 into Experts. Back in MT5, right-click Expert Advisors in the Navigator and choose Refresh.




Step 4 — Allow DLL imports

In MT5, choose Tools → Options (Ctrl+O).



On the Experts tab, tick Allow algorithmic trading and Allow DLL imports. BlackBox uses DLL only to connect through Windows; it never downloads or installs anything.


Prefer not to allow DLL? Tick Allow WebRequest for listed URL and add https://www.indicatorfree.com instead. Doing both is fine. Press OK.



Step 5 — Attach the EA and paste your key

Drag IndicatorFree-BlackBox from the Navigator onto one chart — one chart covers the whole account. On the Common tab, check that Allow DLL imports is ticked.

On the Inputs tab, paste your key into the first line, Your BlackBox key. Leave the rest as it is. Press OK.




Step 6 — Check the panel

The BlackBox panel appears in the chart corner. The first upload arrives within minutes, or press Send now. After that BlackBox syncs about once an hour, sooner after news or a spread spike.

Fills today — fills recorded today; Slippage today — money lost or gained to slippage (fills worse / better); Spread paid today — spread cost; Spread spikes — sharp spread widenings; Last caught — the latest event; Synced — the last upload.

When a new version is out, a gold Update line appears and MT5 alerts you once. Download it from your BlackBox page and copy it over the old file in Experts. BlackBox never updates itself.



Status shows a problem?

Enter your BlackBox key — the key is missing on the Inputs tab.

Allow DLL imports — repeat Step 4, or add the site to the WebRequest list.

No connection, retrying — the internet dropped for a while (sleep, network). Fills are still recorded and queued, and go out as soon as the connection is back.

Your data: www.indicatorfree.com → My account → BlackBox. BlackBox only shows what was recorded — the decision is yours.